

# Magento 2.x REST API

## Introduction

Instructions in this document describes how to create a new REST User on Magento Store as well as how to create a new connection to link your online store.

This document highlights the steps and importance of specific fields that are necessary for creating a new user on Magento Store and for creating a new connection with your online store.

## Online Magento Store Setting for API User

When your online store is installed, your login credentials have complete administrative access. Best approach is to create another account with complete administrative permissions. You can create more user accounts for your team with restricted roles.

### På denna sida:


- [Introduction](#)
- [Online Magento Store Setting for API User](#)
  - [1. Create New User](#)
  - [2. Assign the Role](#)
- [External System Connectors - XTND Backend](#)
  - [1. Create New Connection](#)
  - [2. Edit Synchronization Schedule](#)
    - [Products](#)
    - [Orders](#)

## 1. Create New User

We need to follow following steps to create New User.

1. On the Admin menu, select **System > Permissions > All Users**.
2. Click on the **Add New User** button.

A form opens where you need to enter Account Information.



a. Enter the **User Name** for the account.

- Username should be easy to remember. Example: if username is 'xyz', you login as 'xyz'.
- Username is used as **Access token** on Backend's side when we create a connection.

b. Enter First Name, Last Name.

c. Enter Email Address.

- Email Account must be different from the one associated with your original Admin Account.

d. Enter Password

- Password is used a **Secret** on Backend's side when we create a connection.


e. Select This Account is to 'Active'.

f. Enter Password of Current User in the password field.

## 2. Assign the Role

The following steps explain how to assign the role.

1. In the User information panel on the left, click **User Role**. List of roles will appear.
2. Select Administrators (Initially, this will be the only role available).



3. When complete, click on the 'Save User' button.

You now have two accounts with administrator access.


## External System Connectors - XTND Backend

XTND Backend helps you to manage sales orders, products, shipments and accounts of your online stores, like Magento, Shopify, Fortnox etc. For this, you need to connect/link your online store with XTND Backend.

### 1. Create New Connection

The following steps explain how to create a new connection.

1. Click on **External System Connectors** from **Settings**.
2. Click on the **Create New Connection** button.  
A form opens where you need to enter basic data. Here the information of your online store is used for the connection creation. Important fields to be handled are:
  - a. **External System:** Select name of sales channel, e.g. Magento, Fortnox, Shopify.
  - b. **Access token:** Username of the online store user.
  - c. **API URL:** URL of your online store, e.g. `http://domain.com/index.php/rest/V1`
  - d. **Secret:** Password of the online store user.




3. Click on **'Verify Connection'**. It will verify your information given (External System, Access token, Secret, API URL..) to create a connection.

### 2. Edit Synchronization Schedule

After creating a connection, you can edit a synchronization schedule of all entities like order, product, invoicing, accounting etc. By default, schedule for synchronization is inactive.

## Products


By default, products' synchronization schedule is once a day. You can edit the schedule to your preference:



The screenshot shows a dialog box titled "External system connectors" with a sub-section for "Product". Under "Schedule for synchronization", there are three radio buttons: "Daily" (selected), "Weekly", and "Hourly". Below these is an "Active" checkbox which is checked. The "Start date" is set to "2/27/2017" and the "Time of day" is set to "8:05 AM". At the bottom, there are "Cancel" and "Save" buttons.

## Orders

By default, orders are fetched every hour. You can edit the schedule to your preference:



The screenshot shows a dialog box titled "External system connectors" with a sub-section for "Order". Under "Schedule for synchronization", there are three radio buttons: "Daily", "Weekly", and "Hourly" (selected). Below these is an "Active" checkbox which is unchecked. The "Start date" is set to "2/27/2017" and the "Time of day" is set to "8:05 PM". At the bottom, there are "Cancel" and "Save" buttons.